PD ShippingCom (Reference Guide)

For use with all versions of PD Shipping Component Revised: 2/5/19

PDshop.com / Copyright 2019 All Rights Reserved.

Table of Contents

Table of Contents	2
Getting Started	
PDShippingCom Namespace PDFunctions Class	3
getShippingServices Function	4
Function Syntax	
Public Variables	
DataTable columns	6
Sample Codebehind	7
VB.NET Example	7
VB.NET Example C# Example	8
Optional functions	9
DisplayService RenameService	
RenameService	
getstatelist	
getstatelist getcountrylist	
Terms & Conditions	

Getting Started

This Guide is intended for users with at least some basic ASP.NET (VB.NET or C#) experience. The language and examples in this document are geared toward individuals with some level of prior programming or web development experience.

PDShippingCom Namespace

In order to use any of these functions in your own project or .aspx, .vb, .cs file, you may want to reference the Namespace. Below are examples.

C# Codebehind Example:

using PDShippingCom;

VB.NET Codebehind Example :

Imports PDShippingCom

Importing directly into a .aspx page:

<%@ Import Namespace="PDShippingCom" %>

PDFunctions Class

All functions discussed in this document are in the PDFunctions Class.

Below are some examples of how you access the functions on your page or .vb/.cs file.

C# Example:

PDShippingCom.PDFunctions pd = new PDShippingCom.PDFunctions();

VB.NET Example:

Dim pd As New PDShippingCom.PDFunctions

getShippingServices Function

When called, this function will contact the shipping companies and return a DataTable with available services and rates. The carriers and services that are returned is determined by the values you set in a number of public variables.

Function Syntax

VB.NET

Dim pd As New PDShippingCom.PDFunctions yourrepeater.DataSource = pd.getShippingServices() yourrepeater.DataBind()

<u>C#</u>

PDShippingCom.PDFunctions pd = new PDShippingCom.PDFunctions(); yourrepeater.DataSource = pd.getShippingServices(); yourrepeater.DataBind();

Public Variables

Below is a list of all the variables that you would set before calling this function. Most variables are strings, be sure to convert your numeric values to a string if necessary.

<u>Variable</u>	Example Value	Type	Description/Notes	
sFromstreet1	555 Test Street	String	Origin Street	
sFromcity	New York	String	Origin City	
sFromstate	NY	String	Origin State/Province (2 digit abbreviation)	
sFromcountry	US	String	Origin Country Code (2 digit abbreviation)	
sFromZip	10001	String	Origin Zip/Postal code	
sFromcountryname	United States	String	Origin Country Name	
sTocity	New York	String	Destination City	
sTostate	NY	String	Destination State/Province (2 digit abbreviation)	
sTocountry	US	String	Destination Country Code (2 digit abbreviation)	
sTocountryname	United States	String	Destination Country Name	
sTozip	10001	String	Destination Zip/Postal code	
PackageWeight	1.5	String	Package Weight (in decimal form)	
PackageL	10	String	Package Length	
PackageW	10	String	Package Width	
PackageH	10	String	Package Height	
PackageG	10	String	Package Girth (applies to USPS only)	
PackageValue	100.01	String	Package Value (for insurance purposes)	
dimensionunits	IN	String	Unit of Measure for dimensions, IN or CM (Inches	
			or Centimeters)	
weightunits	LBS	String	Unit of Measure for weight, LBS or KG	
isresidentail	True	Bool	Residential flag, set to True for packages	
			shipping to a Residential address	
usps_enabled	True	Bool	Sets whether USPS rates are enabled. True or	
			False	
uspslogin	ABCD123456	String	USPS Web Tools Login, can also be set in your	
			web.config file	
uspstestmode	True	Bool	USPS Test mode. When set to True, all requests	
			are sent to the USPS development servers. Can	
			also be set in your web.config	

uspssize	Regular	String	USPS size setting, Regular or Large
uspscontainer	RECTANGULAR	String	USPS container setting, RECTANGULAR, or
			NONRECTANGULAR (applies to Large packages
			only)
uspsmachine	False	String	USPS machinable setting, True or False
			(recommended)
uspsbox	USPSD-0	String	USPS box setting, leave blank to retrieve rates
			for all available services. Or, enter service codes
			separated by commas. ex USPSD-0,USPSD-
	T	D I	1,USPSD-3
ups_enabled	True	Bool	Sets whether UPS rates are enabled. True or
unclogin	ABC123456	Ctring	False
upslogin	ABC123430	String	UPS API login, you may also set it in your web.config
upslicense	ABC123456	String	UPS API license, you may also set it in your
ирэпсензе	ADC125450	Jung	web.config
upspass	ABC123456	String	UPS API password, you may also set it in your
ирэризэ	7.56123 130	String	web.config
upstestmode	True	Bool	UPS Test mode. When set to True, all requests
apoteotimode	1.46	200.	are sent to the UPS development servers. Can
			also be set in your web.config
upspickuptype	01	String	UPS pickup type setting, enter 01 for Daily
			Pickup, 03 for Customer Counter, or 11 for
			Suggested Retail Rate
upspacktype	00	String	UPS package type setting, enter 00 for
			Unknown/Your own, 01 for UPS Letter, 02 for
			UPS Tube, 04 for UPS Pak, 21 for UPS Express
			Box, 24 for UPS 25KG Box, or 25 for UPS 10KG
			Box
upsoversize	0	String	UPS oversize setting. Values should be 0 for
			Standard, 1 for Oversize 1, 2 for Oversize 2, or 3
	Turis	Deel	for Oversize 3
upsinsure	True	Bool	UPS insurance setting, set to True to automatically Add UPS Insurance in returned rate
upsaddhand	True	Bool	UPS handling setting, set to True to include UPS
upsauuriariu	True	БООІ	'Additional Handling' in returned rate
fedex_enabled	True	Bool	Sets whether FedEx rates are enabled. True or
reacx_enablea	Truc	Door	False
fedexkey	ABC123456ABC123456	String	FedEx API Key, can also be set in your
	7.20220 1007120220 100	- Cug	web.config
fedexpass	ABC123456ABC123456	String	FedEx API Password, can also be set in your
·			web.config
fedexacc	ABC123456ABC123456	String	FedEx API Account Number, can also be set in
			your web.config
fedexmeter	ABC123456ABC123456	String	FedEx API Meter, can also be set in your
			web.config
fedextestmode	True	Bool	FedEx Test mode. When set to True, all requests
			are sent to the FedEx development servers. Can
			also be set in your web.config
fedexpickup	REGULAR_PICKUP	String	FedEx pickup setting. Enter
			BUSINESS_SERVICE_CENTER, DROP_BOX,
			REGULAR_PICKUP, REQUEST_COURIER, or
fodovinyoissal	ACCOUNT	Ctuin -	STATION Enter ACCOUNT
fedexinvoiced	ACCOUNT YOUR_PACKAGING	String	FedEx Invoice setting. Enter ACCOUNT FedEx package setting, Enter YOUR_PACKAGING,
fedexpack	TOUK_FACKAGING	String	FEDEX_10KG_BOX, FEDEX_25KG_BOX,
			FEDEX_BOX, FEDEX_ENVELOPE, FEDEX_PAK, or
			FEDEX_TUBE
	1	ı	FDFV_ ODF

fedexinsure	True	Bool	FedEx insurance setting, set to True to automatically Add Insurance to returned rate
formerror		String	This is variable will be populated with any messages after you call the getShippingServices function.

DataTable columns

Below is a list of all the columns that will be returned after calling this function.

<u>Variable</u>	Example Value	<u>Type</u>	Description/Notes
carrier	USPS	String	Carrier type, USPS, UPS, or FEDEX
name	Priority Mail Express 1-Day™	String	Service Name
rate	27.5	Decimal	Cost of Service/Rate, as a decimal with no formatting
rateformatted	\$27.50	String	Cost of Service/Rate, formatted as currency
servicecode	USPSD-1	String	A unique code assigned to each service, examples: USPSD-1, UPS-01, FEDEX-SOMENAME

Sample Codebehind

Below is an example of a typical codebehind that uses the PDShippingCom namespace and PDFunctions class.

VB.NET Example

End Class

```
Partial Class Example
  Inherits System.Web.UI.Page
  Protected Sub GetShipping(ByVal sender As Object, ByVal e As EventArgs)
     'Create an instance of the PD Shipping Functions
     Dim pd As New PDShippingCom.PDFunctions
     'Set Origin Address
     pd.sFromstreet1 = fromstreet1.Text
     pd.sFromcity = fromcity.Text
     pd.sFromstate = fromstate.SelectedValue
     pd.sFromcountry = fromcountry.SelectedValue
     pd.sFromcountryname = fromcountry.SelectedItem.Text
     pd.sFromZip = fromzip.Text
     'Set Destination Address
     pd.sTocity = city.Text
     pd.sTostate = state.SelectedValue
     pd.sTocountry = country.SelectedValue
     pd.sTocountryname = country.SelectedItem.Text
     pd.sTozip = zip.Text
     'Set Package details
     pd.PackageWeight = packageweight.Text
     pd.PackageL = packageL.Text
     pd.PackageW = packageW.Text
     pd.PackageH = packageH.Text
     pd.PackageG = packageG.Text
     pd.PackageValue = packagevalue.Text
     pd.dimensionunits = dimensionunit.SelectedValue
     pd.weightunits = weightunit.SelectedValue
     If isresidential.Checked = True Then
       pd.isresidentail = True
     End If
     'USPS specific settings
     pd.uspssize = uspssize.SelectedValue
     pd.uspscontainer = uspscontainer.SelectedValue
     pd.uspsmachine = uspsmachine.SelectedValue
     pd.uspsbox = uspsbox.SelectedValue
     'Set which carriers you want to get rates from, UPS, USPS, FedEx
     pd.usps_enabled = True
     'Call the getShippingServices function to bind the data to your page in a repeator or datalist
     shippingservices.DataSource = pd.getShippingServices()
     shippingservices.DataBind()
  End Sub
```

7

C# Example

```
using System;
using System.Collections.Generic;
using System.Web;
using System.Web.UI;
using System.Web.UI.WebControls;
partial class _Default : System.Web.UI.Page
  protected void GetShipping(object sender, EventArgs e)
     //Create an instance of the PD Shipping Functions
     PDShippingCom.PDFunctions pd = new PDShippingCom.PDFunctions();
     //Set Origin Address
     pd.sFromstreet1 = fromstreet1.Text;
     pd.sFromcity = fromcity.Text;
     pd.sFromstate = fromstate.SelectedValue;
     pd.sFromcountry = fromcountry.SelectedValue;
     pd.sFromcountryname = fromcountry.SelectedItem.Text;
     pd.sFromZip = fromzip.Text;
     //Set Destination Address
     pd.sTocity = city.Text;
     pd.sTostate = state.SelectedValue;
     pd.sTocountry = country.SelectedValue;
     pd.sTocountryname = country.SelectedItem.Text;
     pd.sTozip = zip.Text;
     //Set Package details
     pd.PackageWeight = packageweight.Text;
     pd.PackageL = packageL.Text;
     pd.PackageW = packageW.Text;
     pd.PackageH = packageH.Text;
     pd.PackageG = packageG.Text;
     pd.PackageValue = packagevalue.Text;
     pd.dimensionunits = dimensionunit.SelectedValue;
     pd.weightunits = weightunit.SelectedValue;
     if (isresidential.Checked == true)
     {
       pd.isresidentail = true;
     }
     //USPS specific settings
     pd.uspssize = uspssize.SelectedValue;
     pd.uspscontainer = uspscontainer.SelectedValue;
     pd.uspsmachine = uspsmachine.SelectedValue;
     pd.uspsbox = uspsbox.SelectedValue;
     //Set which carriers you want to get rates from, UPS, USPS, FedEx
     pd.usps_enabled = true;
     //Call the getShippingServices function to
     shippingservices.DataSource = pd.getShippingServices();
     shippingservices.DataBind();
```

Optional functions

DisplayService

See examples in sample .vb and .cs files

RenameService

See examples in sample .vb and .cs files

getstatelist

See examples in sample .vb and .cs files

getcountrylist

See examples in sample .vb and .cs files

Terms & Conditions

This guide is intended for licensed users of our products only.

See the Terms & Conditions on the PDshop website, see https://www.pdshop.com/terms/.

Copyright Notice:

All Text and Images contained on this document is the property of pdshop.com and cannot be reproduced, copied, or used without our written permission.

PDshop.com / Copyright 2019 All Rights Reserved